


Unix & Linux





1 of 2 25/03/2021, 07:10

I'm using this on a daily basis. You need an xorg.conf file, in your Device section you need the following:



"nopowerconnectorcheck" Option "ExactModeTimingsDVI" "ON" Option



Then in your Monitor section place your HorizSync, VertRefresh, and ModeLine Finally in your Screen section add this:

```
Option "AllowEmptyInitialConfiguration" "True"
Option "ConnectedMonitor" "DFP"
Option "UseDisplayDevice" "DFP-0"
Option "ModeValidation" "AllowNonEdidModes"
SubSection "Display"
                  24
       Depth
                   "<Resolution and Refresh from your modeline>"
       Modes
EndSubSection
```

What this does is tells the Nvidia driver that there is a monitor attached, and gives it the information required to start drawing to the frame buffer. No monitor required. I do recommend using x11vnc to do your viewing because it polls the screen and is much more responsive to screen changes than any other linux vncserver.

Share Improve this answer Follow

answered Feb 19 '19 at 20:33



2 of 2 25/03/2021, 07:10